

LinuxLIVE User Guide

Table Of Contents

About LinuxLIVE	1
Installation and Registration	2
Pre-Installation Instructions.....	2
Root Installation.....	2
Installation.....	2
Uninstallation	2
Non Root Installation	2
Uninstallation	2
Registering LinuxLIVE	3
Running LinuxLIVE	5
Launching LinuxLIVE.....	5
Creating Your First LIVE Session	5
Exiting LinuxLIVE	6
Connections	7
Connection Menu	7
Launching Connections	7
Disconnecting	7
Connection Methods.....	7
Localhost.....	8
Rexec.....	8
SSH	8
Sessions	10
Session Menu.....	10
Defining a Session.....	10
Saving Sessions.....	11
Session Options	11
Indirect Sessions on Gateway Servers.....	12
Multi-user Instances	12
Instances.....	13
Instance Menu	13
Suspending Instances	13
Manually Suspending Instances.....	13
Resuming Instances	14
Terminating Instances	14
Terminating Instances from the Command Line	14
Contact StarNet.....	15

Table Of Contents

StarNet Main Office 15
Customer Support..... 15
Sales Department..... 15

About LinuxLIVE

For 20 years, StarNet has been a leading provider of software to connect Windows PCs to Unix and Linux systems. Over the past 10 years, an increasing number of engineers and other computer users have been switching to Linux workstations. While many X applications have been ported to Linux and can run locally on the workstation, Linux users also need to access other applications. Those connections, especially VPN and other WAN connections, are just as vulnerable to fatal network or power interrupts as connections from Windows PCs.

First developed in 2008 for StarNet's X-Win32 Windows users, LinuxLIVE now offers Linux users the same set of next-generation LIVE session capabilities when connecting to remote servers. These highly productive features include:

Installation and Registration

Pre-Installation Instructions

LinuxLIVE can be run on any system which has gcc 3.4 or later installed on it. Users who are not running redhat systems (or its variants) should download the RHEL4 version of LinuxLIVE. Fedora 7 and greater users should download the RHEL5 version.

Root Installation

Installation

1. Download LinuxLIVE
2. Log in as root.
3. `rpm -i LinuxLIVE-<version>-<build number>-<os>.<arch>.rpm`
where
 - <version>: current version
 - <build number>: current build number
 - <os>: Operating system (eg. rhel4 or rhel5)
 - <arch>: hardware architecture (eg. i386)

Uninstallation

1. Log in as root
2. `rpm -e LinuxLIVE`

Non Root Installation

1. Download LinuxLIVE
2. `tar -xzf LinuxLIVE-<version>-<build number>-<os>.<arch>.tar.gz`
 - <version>: current version
 - <build number>: current build number
 - <os>: Operating system (eg. rhel4 or rhel5)
 - <arch>: hardware architecture (eg. i386)

Uninstallation

1. Delete the LinuxLIVE directory and its contents


Registering LinuxLIVE

Unregistered copies of LinuxLIVE run with limited functionality. Connections can be created edited and launched and sessions can be created and edited. However Instances are disabled until LinuxLIVE has been registered.

1. Launch LinuxLIVE
2. Select **Help > Register** to bring up the Registration dialog

3. Enter the license key in the VN field.
4. For users with a connection to the outside internet Press **Next** and skip to step .
5. For users without an outside internet connection select **I want to register manually** and press **Next**
6. Copy the key and follow the instructions as stated on the form. Press **Next**

7. Paste the response key which was attained from the website. Press **Next**



8. Press **Finish** to complete registration

Running LinuxLIVE

LinuxLIVE creates sessions based on the LIVE protocol which allow session persistency. These sessions can be suspended and resumed at a later time or terminated ending the session. The LIVE Server runs on the remote host allowing the session to stay active even after the LIVE client has disconnected.

The following Table Shows some of the advantages of LIVE Sessions.

Persistence	<p>Session persistency means that even though your connection has disconnected from the host machine, the LIVE session is still actively running on the host machine.</p> <p>For example, you can start a long running compilation project through a LIVE session, suspend the session, and reconnect at a later time when the compilation has finished. With other connection methods closing the window will automatically terminate your session requiring you to start the compilation over from the beginning.</p>
Mobility	<p>All LIVE Session are stored on the remote Unix machine. Users can reconnect from any machine which has the LIVE client installed by simply logging into the machine using LIVE. A user can even start his session on the Unix machine, suspend it and reconnect to it from any machine running a LIVE client.</p>
Collaboration	<p>Multiple users can now connect to the same LIVE session to work and collaborate together at the same time. Users can choose to take control of the desktop, or they can simply view the desktop itself.</p>
Compression	<p>LIVE Sessions use a special protocol which cuts down on the amount of round trip X traffic thus increasing performance and lowering bandwidth.</p>


LIVE sessions require the LIVE server component to be installed on the remote UNIX/Linux host in order to function

Launching LinuxLIVE

- **Root Installation:** From a terminal, run the command: **llapp**
- **Nonroot Installation:**
 1. After extracting the files, a LinuxLIVE directory will be created.
 2. cd LinuxLIVE/bin
 3. run the command: **lllaunch app**

Creating Your First LIVE Session

1. Launch LinuxLIVE. The LinuxLIVE interface is shown below



2. Select **Connection > New**
3. Create a New Connection (See Connections for details)
4. Double Click on the new connection to Connect to your remote system
5. Select **Session > New**
6. Create a New Session (See Sessions for details)
7. Double Click on the new session to launch an instance.
8. Instances can be suspended, resumed or terminated by selecting the option from the Instance Menu (See Instances for details)

Exiting LinuxLIVE

Select **File > Close** to exit LinuxLIVE. All connections will be disconnected and all running Instances will be Suspended

Connections

In order to run a LIVE Session, a connection must first be made to the LIVE Server. The LIVE Server component can be installed either locally or remotely on a Linux or Unix system



Connection Menu

Menu Item	Description
New	Create a new Connection
Edit	Edit the currently selected Connection
Delete	Delete the currently selected Connection
Connect	Connect to the currently selected Connection
Disconnect	Disconnect from the currently Selected Connection
Show Log	Show the Connection dialog of the Connection

Launching Connections

Double click on a Connection to Launch the Connection. The running instances will be displayed in the Instance Browser, while the currently defined sessions will be displayed in the Session Browser.

Disconnecting

Right click on the Connection and select Disconnect to close the connection

Connection Methods

There are several methods to connect to a local or remote LIVE Server

Localhost

Connect to your local linux system.

Property	Description
SCI	Remote Server Interface Program (rxlaunch sci5). This is the launcher program used to start the LIVE Server. If installed as root, or if rxlaunch is located in your system \$PATH variable, this property does not need to be edited. If the LIVE Server is installed in a non standard location, (such as a nonroot install), provide the fully qualified PATH to the rxlaunch application.

Rexec

Connect to a remote Linux system using the rexec protocol. On most modern Linux systems rexec is disabled by default.

Property	Description
Host	The remote host or IP address where the LIVE Server is located
Login	The username on the remote system
Password	The password on the remote system
Speed	The Connection Speed for the LIVE Server which optimizes the graphical/compression settings of LIVE sessions according to the type of Network connection used. Change the option according to the speed of your network.
SCI	Remote Server Interface Program (rxlaunch sci5). This is the launcher program used to start the LIVE Server. If installed as root, or if rxlaunch is located in your system \$PATH variable, this property does not need to be edited. If the LIVE Server is installed in a non standard location, (such as a nonroot install), provide the fully qualified PATH to the rxlaunch application.

SSH

Connect to a remote Linux system using the SSH protocol. On most modern Linux systems SSH is enabled by default.

Property	Description
Host	The remote host or IP address where the LIVE Server is located
Port	The port that the remote host is listening on. The default value is the


well known port number of the specified protocol. Only change this number if you know that the remote host is listening on a different port for your connection.

- Login** The username on the remote system
- Speed** The Connection Speed for the LIVE Server which optimizes the graphical/compression settings of LIVE sessions according to the type of Network connection used. Change the option according to the speed of your network.
- Tunnel** Enable SSH tunnelling. Check this option if you want to encrypt your DISPLAY encrypted through ssh. This is often needed when connecting through a firewall as the ssh port may be the only port open to the outside.
- SCI** Remote Server Interface Program (**rxlaunch sci5**). This is the launcher program used to start the LIVE Server. If installed as root, or if rxlaunch is located in your system \$PATH variable, this property does not need to be edited. If the LIVE Server is installed in a non standard location, (such as a nonroot install), provide the fully qualified PATH to the rxlaunch application.

Sessions

LIVE Sessions are templates stored on the remote Unix/Linux system which contain the default information to Launch a LIVE Session Instance.

To launch a new Instance of a LIVE Session, double click on the session icon, or right click on the session and press *Launch*




Session Menu

Menu Item	Description
New	Create a new Session
Edit	Edit the currently selected Session
Delete	Delete the currently selected Session
Launch	Launch the currently selected Session

Defining a Session

1. Right click on the Sessions window and select *New*.

- The following screen appears



The screenshot shows a configuration window for a session. It includes the following elements:

- Name:** A text input field containing "Default".
- Desktop:** A dropdown menu showing "KDE" with a small icon to the left.
- Allow Sharing:** A checkbox that is currently unchecked.
- Window Mode:** A dropdown menu showing "Default".
- Size:** A section containing two spinners: "Width" set to 1024 and "Height" set to 768.

- Select *Save* or *Save as Global* to save your session

Saving Sessions

LIVE Sessions can be global to all users or local to the current user. When defining a new session two options are available: *Save* and *Save as Global*. The sessions are stored in different directories specified in the LIVE.conf configuration file. Users must have proper directory permissions to *Add*, *Edit*, or *Remove* sessions

Session Options

Property	Description
Name	The name of the session.
Desktop	<p>Three standard Unix/Linux desktops (GNOME, KDE, CDE) are included by default. A fourth type Custom allows for individual applications (specified in the field to the right) to be launched from the LIVE Server.</p> <p>Note: LIVE sessions assume that the desktop's launching application is located in the user's \$PATH. If not, the fully qualified path name must be added in the field to the right.</p>
Allow Sharing	Allow multiple users to connect to a running instance.
Window Mode	<p>The display mode of the Instance</p> <ul style="list-style-type: none"> Default: LIVE Instances run in a window whose initial size is specified in the Size options Fullscreen: LIVE Sessions are borderless taking up the entire screen Rootless: Each application runs in its own individual window
Height	Window Height in pixels

Width	Window Width in pixels
--------------	------------------------

Indirect Sessions on Gateway Servers

For users who want to install the LIVE Server on a gateway and then connect to the internal network using ssh, an Indirect method is recommended. Launching an instance of the session will automatically ssh to the internal machine thus indirectly connecting.

1. Create a new LIVE Session
2. Select Desktop: *Custom*
3. Enter the following command
ssh -X [-l Username] Hostname Command

-l Username: The username on the remote host. This can be different than the username of the LIVE session. If -l Username is omitted, the current user's name will be submitted.

Hostname: The remote host specified as a hostname or IP address.

Command: The remote command to be run, for example xterm or gnome-desktop.

4. The user will be prompted for a password when connecting to the second host.







Multi-user Instances

Multiple users can connect to a running instance if Sharing is enabled in the LIVE Session. To connect to a shared instance select the *Shadow* button from the *Instance* menu and enter the secret key that was provided to you by the creator of the instance.

Instances

The top window shows all the currently running instances of a LIVE Session. The status column shows the current status of each instance. Running sessions are currently connected. Suspended sessions are currently disconnected and processing in the background. Working sessions are in the intermediate state of running and suspended. Multiple instances of each session are allowed and defined by their start time. If there are currently no running instances, this window will appear blank.

Double click on an instance to connect.

Session	Status	Started	Last Suspended	Last Resumed	Window Size
 Default	 Running	2:28 AM	2:31 AM	2:32 AM	
 KDE Sessi...	 Running	2:28 AM	2:31 AM	2:32 AM	794x524
 My Gnom...	 Suspended	2:29 AM	2:29 AM		794x524

Instance Menu

Menu Item	Description
Resume	Resume the Selected Instance
Suspend	Suspend the Selected Instance
Terminate	Terminate the Selected Instance
Shadow	Connect to a Shared running Instance. The secret key is displayed when the Master Session is first launched.

Suspending Instances

Instances are automatically suspended when the LIVE server detects that a client has disconnected, either manually, or by an error (such as the network getting disconnected). Users can reconnect to a suspended instance without loss of data.

Manually Suspending Instances

Instances can be suspended by right clicking on a running instance in the Instance Browser and press *Suspend* to suspend the instance.

Instances can also be suspended by using a key combination.

1. Enter the key combination CONTROL+ALT+T to bring up the



Suspend prompt.

2. Select the *Suspend* button to suspend the instance
NOTE: Closing the Desktop window also brings up this dialog

Resuming Instances

Suspended Instances are marked with a red circle in the Instance Browser. To resume an Instance, double click on the Suspended Instance

Terminating Instances

Instances can be terminated by right clicking on a running instance in the Instance Browser and press Terminate to terminate the instance. If running a desktop log out using the standard Unix/Linux Desktop logout procedure (for example pressing the logout button in GNOME).

Terminating Instances from the Command Line

Each running instance runs its own nxagent process. Sending a TERM signal to an nxagent will terminate the associated session. The pid of an nxagent associated with a given session can be found using ps (or pidof, pgrep etc).

The rxserver.log file contains both the pid and the associated display number of a specific instance in the following lines.

Info: Proxy running in server mode with pid 'pid_number'

Info: Waiting for connection from '127.0.0.1' on port '<Display_number + 4000>'

NOTE: It is not recommended to terminate desktop instances from the command line as each desktop has it's own logout procedure which will be skipped if the nxagent process is killed possibly causing data errors

Contact StarNet

StarNet Main Office

Web Site

<http://www.starnet.com>

Address

StarNet Communications
1270 Oakmead Parkway, Suite 301
Sunnyvale, CA 94085-4044

Customer Support

Web Site

<http://www.starnet.com/support>

- FAQs, latest upgrades, and new information regarding X-Win32's most recent developments.
- A customer support ticket system you can access online through X-Win32.

Sales Department

Telephone

(408) 739 0881

The Sales Department is available 8:00 AM - 5:00 PM PST, Monday through Friday.

Fax

(408) 739 0936

Email

SalesDept@StarNet.com